

Data Loader Guide

Version 50.0, Winter '21





CONTENTS

Chapter 1: Data Loader
Chapter 2: When to Use Data Loader
Chapter 3: Installing Data Loader
Install Data Loader on macOS
Install Data Loader on Windows
Considerations for Installing Data Loader
Chapter 4: Configure Data Loader
Data Loader Behavior with Bulk API Enabled
Configure the Data Loader to Use the Bulk API
Chapter 5: Using Data Loader
Data Types Supported by Data Loader
Export Data
Define Data Loader Field Mappings
Insert, Update, or Delete Data Using Data Loader
Perform Mass Updates
Perform Mass Deletes
Upload Attachments
Upload Content with the Data Loader
Review Data Loader Output Files
Data Import Dates
View the Data Loader Log File
Configure the Data Loader Log File
Chapter 6: Running in Batch Mode (Windows Only)
Installed Directories and Files
Encrypt from the Command Line
Upgrade Your Batch Mode Interface
Run Batch File With Windows Command-Line Interface
Configure Batch Processes
Data Loader Process Configuration Parameters
Data Loader Command-Line Operations
Configure Database Access
Spring Framework
Data Access Objects
SQL Configuration
Map Columns

Contents

Run Individual Batch Processes
Chapter 7: Command-Line Quick Start (Windows Only)
Data Loader Command Line Introduction
Prerequisites
Step One: Create the Encryption Key File
Step Two: Create the Encrypted Password
Step Three: Create the Field Mapping File
Step Four: Create the Configuration File
Step Five: Import the Data
Appendix A: Data Loader Third-Party Licenses
Index52

CHAPTER 1 Data Loader

Data Loader is a client application for the bulk import or export of data. Use it to insert, update, delete, or export Salesforce records.

When importing data, Data Loader reads, extracts, and loads data from comma-separated values (CSV) files or from a database connection. When exporting data, it outputs CSV files.



Note: If commas aren't appropriate for your locale, use a tab or other delimiter. Specify your delimiter in Data Loader Settings (**Settings** | **Settings**).

You can use Data Loader in two different ways:

- User interface—When you use the user interface, you work interactively to specify the configuration parameters, CSV files used for import and export, and the field mappings that map the field names in your import file with the field names in Salesforce.
- Command line (Windows only)—When you use the command line, you specify the configuration, data sources, mappings, and actions in files. This enables you to set up Data Loader for automated processing.

Data Loader offers the following key features:

- An easy-to-use wizard interface for interactive use
- An alternate command-line interface for automated batch operations (Windows only)
- Support for large files with up to 5 million records
- Drag-and-drop field mapping
- Support for all objects, including custom objects
- Can be used to process data in both Salesforce and Database.com
- Detailed success and error log files in CSV format
- A built-in CSV file viewer
- Support for Windows and Mac

To get started, see the following topics:

- When to Use Data Loader
- Considerations for Installing Data Loader
- Note: In previous versions, Data Loader has been known as "AppExchange Data Loader" and "Sforce Data Loader."

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

CHAPTER 2 When to Use Data Loader

Data Loader complements the web-based import wizards that are accessible from the Setup menu in the online application. Refer to the following guidelines to determine which method best suits your business needs:

Use Data Loader when:

 You need to load 50,000 to 5,000,000 records. Data Loader is supported for loads of up to 5 million records. If you need to load more than 5 million records, we recommend you work with a Salesforce partner or visit the AppExchange for a suitable partner product.

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise,
Performance, Unlimited,
Developer, and
Database.com Editions

- You need to load into an object that is not yet supported by the import wizards.
- You want to schedule regular data loads, such as nightly imports.
- You want to export your data for backup purposes.

Use the import wizards when:

- You are loading less than 50,000 records.
- The object you need to import is supported by import wizards. To see what import wizards are
 available and thus what objects they support, from Setup, enter Data Management in the
 Quick Find box, then select Data Management.
- You want to prevent duplicates by uploading records according to account name and site, contact email address, or lead email address.

For more information about the import wizards, see Import Data Into Salesforce.

CHAPTER 3 Installing Data Loader

In this chapter ...

- Install Data Loader on macOS
- Install Data Loader on Windows
- Considerations for Installing Data Loader

You can use Data Loader to insert, update, delete, and export Salesforce records.

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

Installing Data Loader Install Data Loader on macOS

Install Data Loader on macOS

You can use Data Loader to insert, update, delete, and export Salesforce records. To use it, you install it on your macOS computer.

- 1. Install Zulu OpenJDK version 11for macOS using the .DMG file.
- 2. From Setup, download the Data Loader installation file.
- 3. Right-click the .zip file and select Extract All.
- **4.** In the Data Loader folder, double-click the **installer.command** file. If you can't open the file because of an unidentified developer message, press the Control key while clicking the **installer.command** file, and select **open** from the menu.
- **5.** Specify where to install Data Loader.
- **6.** Specify whether to add a Data Loader launch icon on your desktop or Applications folder. Data Loader completes the installation.

To run Data Loader, use the Data Loader desktop icon, Applications folder, or dataloader.command in your installation folder. If Zulu OpenJDK is not found, a message prompts you to download and install it.

Ø

Note: To continue using your settings from an earlier Data Loader version in version 45 and later, migrate your config and log files after installation. Search for config.properties and log-config.xml, and copy or move the files to your current Data Loader's /config folder.

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, Developer, and Database.com Editions

USER PERMISSIONS

To access the page to download Data Loader:

Modify All Data

To use Data Loader:

API Enabled

AND

The appropriate user permission for the operation you are doing, for example, Create on accounts to insert new accounts

AND

Bulk API Hard Delete (only if you configure Data Loader to use Bulk API to hard-delete records)

Install Data Loader on Windows

You can use Data Loader to insert, update, delete, and export Salesforce records. To use it, you install it on your Windows computer.

- 1. Install Zulu OpenJDK version 11 for Windows using the .MSI file.
- 2. From Setup, download the Data Loader installation file.
- 3. Right-click the .zip file and select Extract All.
- **4.** In the Data Loader folder, double-click the **install.bat** file. If you get an unknown publisher error message, you can ignore it and run the file.
- **5.** Specify where to install Data Loader, and select whether to overwrite an existing Data Loader installation.
- **6.** Specify whether to create a Data Loader launch icon on your desktop or a start menu shortcut. Data Loader completes the installation.

To run Data Loader, use the Data Loader desktop icon, start menu entry, or the dataloader.bat file in your installation folder. If Zulu OpenJDK is not found, a message prompts you to download and install it.

Ø

Note: To continue using your settings from an earlier Data Loader version in version 45 and later, migrate your config and log files after installation. Search for config.properties and log-config.xml, and copy or move the files to your current Data Loader's /config folder.

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, Developer, and Database.com Editions

USER PERMISSIONS

To access the page to download Data Loader:

Modify All Data

To use Data Loader:

API Enabled

AND

The appropriate user permission for the operation you are doing, for example, Create on accounts to insert new accounts

AND

Bulk API Hard Delete (only if you configure Data Loader to use Bulk API to hard-delete records)

Considerations for Installing Data Loader

Before you download and install Data Loader, understand the system requirements, installation considerations, and login considerations.

System Requirements for Windows

Data Loader is signed for Windows. To use Data Loader for Windows, you need:

- 64-bit Microsoft® Windows® 7, Windows 8, or Windows 10
- 120 MB of free disk space
- 256 MB of available memory
- Zulu OpenJDK version 11



We recommend that you set the JAVA_HOME environment variable to the directory where Zulu OpenJDK is installed. Doing so ensures that you can run Data Loader in batch mode from the command line.

System Requirements for macOS

To use Data Loader for macOS, you need:

- 64-bit macOS El Capitan
- 120 MB of free disk space
- 256 MB of available memory
- Zulu OpenJDK version 11

Installation Considerations

Over time, several versions of the Data Loader client application have been available for download. Some earlier versions were called "AppExchange Data Loader" or "Sforce Data Loader." You can run different versions at the same time on one computer. However, do not install more than one copy of the same version. If you have installed the latest version and want to install it again, first remove the version on your computer.

The latest version is always available in Salesforce. From Setup, enter <code>Data Loader</code> in the Quick Find box, then select **Data Loader**.



Tip: If you experience login issues in the command-line interface after upgrading Data Loader, try encrypting your password again to solve the problem. For information, see Encrypt from the Command Line on page 25.

Note: The Data Loader command-line interface is supported for Windows only.

To change the source code, download the open-source version of Data Loader from https://github.com/forcedotcom/dataloader.

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: **Enterprise**, **Performance**, **Unlimited**, **Developer**, and **Database.com** Editions

USER PERMISSIONS

To access the page to download Data Loader:

Modify All Data

To use Data Loader:

API Fnabled

AND

The appropriate user permission for the operation you are doing, for example, Create on accounts to insert new accounts

AND

Bulk API Hard Delete (only if you configure Data Loader to use Bulk API to hard-delete records)

Login Considerations

- If your organization restricts IP addresses, logins from untrusted IPs are blocked until they're activated. Salesforce automatically sends
 you an activation email that you can use to log in. The email contains a security token that you add to the end of your password. For
 example, if your password is mypassword, and your security token is XXXXXXXXXX, you must enter
 mypasswordXXXXXXXXXX to log in.
- Data Loader version 36.0 and later supports Web Server OAuth Authentication. See OAuth Authentication for more information.
- Data Loader version 36.0 and later supports Salesforce Communities. Communities users always log in with the OAuth option in Data Loader. To enable OAuth for Communities, the user modifies the config.properties file as follows.
 - Change the portion in bold in the following line to the login URL of the community. Don't add a forward slash (/) to the end of the line.

```
sfdc.oauth.Production.server=https\://login.salesforce.com
```

For example:

```
sfdc.oauth.Production.server=https\://CommunitiesSubdomainName.force.com/test
```

Change the portion in bold in the following line to the hostname of the community.

```
sfdc.oauth.Production.redirecturi=https\://login.salesforce.com/services/oauth2/success
```

For example:

```
sfdc.oauth.Production.redirecturi=
https\:/CommunitiesSubdomainName.force.com/services/oauth2/success
```

The config.properties file is in the configs default configuration directory, which is installed in these locations.

- macOS: /Users/{userName}/dataloader/version/configs
- Windows: C:\Users\{userName}\dataloader\version\configs

CHAPTER 4 Configure Data Loader

In this chapter ...

- Data Loader
 Behavior with Bulk
 API Enabled
- Configure the Data Loader to Use the Bulk API

Use the Settings menu to change the Data Loader default operation settings.

- 1. Open the Data Loader.
- 2. Select Settings > Settings.
- 3. Edit the fields as needed.

Field	Description
Batch size	In a single insert, update, upsert, or delete operation, records moving to or from Salesforce are processed in increments of this size. The maximum is 200 records. We recommend a value between 50 and 100. The maximum value is 10,000 if the Use Bulk API
	option is selected.
Insert null values	Select this option to insert blank mapped values as null values during data operations. When you are updating records, this option instructs Data Loader to overwrite existing data in mapped fields.
	This option is not available if the Use Bulk API option is selected. Empty field values are ignored when you update records using the Bulk API. To set a field value to null when the Use Bulk API option is selected, use a field value of #N/A.
Assignment rule	Specify the ID of the assignment rule to use for inserts, updates, and upserts. This option applies to inserts,

EDITIONS

Available in: both Salesforce Classic and Lightning Experience

Field	Description
	updates, and upserts on cases and leads. With the original territory management feature, it also applies to updates on accounts if your organization has territory assignment rules on accounts. The assignment rule overrides Owner values in your CSV file.
Server host	Enter the URL of the Salesforce server with which you want to communicate. For example, if you are loading data into a sandbox, change the URL to https://test.salesforce.com.
Reset URL on Login	By default, Salesforce resets the URL after login to the one specified in Server host. To turn off this automatic reset, disable this option.
Compression	Compression enhances the performance of Data Loader and is turned on by default. You might want to disable compression when debugging the underlying SOAP messages. To turn off compression, enable this option.
Timeout	Specify how many seconds Data Loader waits to receive a response back from the server before returning an error for the request.
Query request size	In a single export or query operation, records are returned from Salesforce in increments of this size. Larger values can improve performance but use more memory on the client.
	The default is 500; the minimum is 200, and the maximum is 2,000. There is no guarantee that the requested batch size requested is the actual batch size; changes are sometimes made to maximize performance.
Generate status files for exports	Select this option to generate success and error files when exporting data.
Read all CSVs with UTF-8 encoding	Select this option to force files to open in UTF-8 encoding, even if they were saved in a different format.
Write all CSVs with UTF-8 encoding	Select this option to force files to be written in UTF-8 encoding.
Use European date format	Select this option to support the date formats dd/MM/yyyy and dd/MM/yyyy HH:mm:ss.

Field	Description
Allow field truncation	Select this option to truncate data in the following types of fields when loading that data into Salesforce: Email, Multi-select Picklist, Phone, Picklist, Text, and Text (Encrypted).
	In Data Loader versions 14.0 and earlier, Data Loader truncates values for fields of those types if they are too large. In Data Loader version 15.0 and later, the load operation fails if a value is specified that is too large.
	Selecting this option allows you to specify that the previous behavior, truncation, be used instead of the new behavior in Data Loader versions 15.0 and later. This option is selected by default and has no effect in versions 14.0 and earlier.
	This option is not available if the Use Bulk API option is selected. In that case, the load operation fails for the row if a value is specified that is too large for the field.
Allow comma as a CSV delimiter	Select this option if your CSV file uses commas to delimit records.
Allow tab as a CSV delimiter	Select this option if your CSV file uses tab characters to delimit records.
Allow other characters as CSV delimiters	Select this option if your CSV file uses a character other than a comma or tab to delimit records.
Other delimiters (enter multiple values with no separator; for example, !+?)	The characters in this field are used only if the Allow other characters as CSV delimiters option is selected. For example, if you use the (pipe) character to delimit data records, enter that character in this field.
Use Bulk API	Select this option to use Bulk API to insert, update, upsert, delete, and hard-delete records. Bulk API is optimized to load or delete many records asynchronously. It's faster than the default SOAP-based API due to parallel processing and fewer network round-trips.
	Warning: You can hard delete records when you configure Data Loader to Use Bulk API. Keep in mind that hard deleted records are immediately deleted and can't be recovered from the Recycle Bin.

Field	Description
Enable serial mode for Bulk API	To use serial processing instead of parallel processing for Bulk API, select this option. Processing in parallel can cause database contention. When contention is severe, the load can fail. Serial mode processes batches one at a time, however it can increase the processing time for a load.
	This option is only available if the Use Bulk API option is selected.
Upload Bulk API Batch as Zip File	Select this option to use Bulk API to upload zip files containing binary attachments, such as Attachment records or Salesforce CRM Content.
	This option is only available if the Use Bulk API option is selected.
Time Zone	Select this option to specify a default time zone.
	If a date value does not include a time zone, this value is used.
	• If no value is specified, the time zone of the computer where Data Loader is installed is used.
	• If an incorrect value is entered, GMT is used as the time zone and this fact is noted in the Data Loader log.
	Valid values are any time zone identifier which can be passed to the Java
	<pre>getTimeZone(java.lang.String) method. The value can be a full name such as America/Los_Angeles, or a custom ID such as GMT-8:00.</pre>
Proxy host	The host name of the proxy server, if applicable.
Proxy port	The proxy server port.
Proxy username	The username for proxy server authentication.
Proxy password	The password for proxy server authentication.
Proxy NTLM domain	The name of the Windows domain used for NTLM authentication.
Start at row	If your last operation failed, you can use this setting to begin where the last successful operation finished.

4. Click **OK** to save your settings.

Data Loader Behavior with Bulk API Enabled

Enabling the Bulk API in Data Loader allows you to load or delete a large number of records faster than using the default SOAP-based API. However, there are some differences in behavior in Data Loader when you enable the Bulk API. One important difference is that it allows you to execute a hard delete if you have the permission and license. See Configure Data Loader on page 8.

The following settings are not available on the **Settings** > **Settings** page in Data Loader when the Use Bulk API option is selected:

Insert null values

This option enables Data Loader to insert blank mapped values as null values during data operations when the Bulk API is disabled. Empty field values are ignored when you update records using the Bulk API. To set a field value to null when the Use Bulk API option is selected, use a field value of #N/A.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, Developer, and Database.com Editions

Allow field truncation

This option directs Data Loader to truncate data for certain field types when the Bulk API is disabled. A load operation fails for the row if a value is specified that is too large for the field when the Use Bulk API option is selected.

Configure the Data Loader to Use the Bulk API

The Bulk API is optimized to load or delete a large number of records asynchronously. It is faster than the SOAP-based API due to parallel processing and fewer network round-trips. By default, Data Loader uses the SOAP-based API to process records.

To configure Data Loader to use the Bulk API for inserting, updating, upserting, deleting, and hard deleting records:

- 1. Open the Data Loader.
- 2. Choose Settings > Settings.
- 3. Select the Use Bulk API option.
- 4. Click OK

Note:

- You can also select the Enable serial mode for Bulk API option.
 Processing in parallel can cause database contention. When contention is severe, the load can fail. Serial mode processes batches one at a time, however it can increase the processing time for a load.
- Caution: You can hard delete records when you configure Data Loader to Use Bulk
 API. Keep in mind that hard deleted records are immediately deleted and can't be
 recovered from the Recycle Bin.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

CHAPTER 5 Using Data Loader

In this chapter ...

- Data Types
 Supported by Data
 Loader
- Export Data
- Define Data Loader Field Mappings
- Insert, Update, or Delete Data Using Data Loader
- Upload Attachments
- Upload Content with the Data Loader
- Review Data Loader Output Files
- Data Import Dates
- View the Data Loader Log File
- Configure the Data Loader Log File

Using Data Loader, you can perform various operations which include exporting data, defining field mappings, inserting, updating, and deleting data, performing mass updates and mass deletes, uploading attachments and content, and reviewing output files.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Data Types Supported by Data Loader

Data Loader supports the following data types:

Base64

String path to file (converts the file to a base64–encoded array). Base64 fields are only used to insert or update attachments and Salesforce CRM Content. For more information, see Upload Attachments on page 20 and Upload Content with the Data Loader on page 21.

Boolean

- True values (case insensitive) = yes, y, true, on, 1
- False values (case insensitive) = no, n, false, off, 0

Date Formats

We recommend you specify dates in the format yyyy-MM-ddTHH: mm:ss.SSS+/-HHmm.

- yyyy is the four-digit year
- MM is the two-digit month (01-12)
- dd is the two-digit day (01-31)
- HH is the two-digit hour (00-23)
- mm is the two-digit minute (00-59)
- ss is the two-digit seconds (00-59)
- SSS is the three-digit milliseconds (000-999)
- +/-HHmm is the Zulu (UTC) time zone offset

The following date formats are also supported:

- yyyy-MM-dd'T'HH:mm:ss.SSS'Z'
- yyyy-MM-dd'T'HH:mm:ss.SSS Pacific Standard Time
- yyyy-MM-dd'T'HH:mm:ss.SSSPacific Standard Time
- yyyy-MM-dd'T'HH:mm:ss.SSS PST
- yyyy-MM-dd'T'HH:mm:ss.SSSPST
- yyyy-MM-dd'T'HH:mm:ss.SSS GMT-08:00
- yyyy-MM-dd'T'HH:mm:ss.SSSGMT-08:00
- yyyy-MM-dd'T'HH:mm:ss.SSS -800
- yyyy-MM-dd'T'HH:mm:ss.SSS-800
- yyyy-MM-dd'T'HH:mm:ss
- yyyy-MM-dd HH:mm:ss
- yyyyMMdd'T'HH:mm:ss
- yyyy-MM-dd
- MM/dd/yyyy HH:mm:ss
- MM/dd/yyyy
- yyyyMMdd

Note the following tips for date formats:

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Using Data Loader Export Data

• To enable date formats that begin with the day rather than the month, select the Use European date format box in the Settings dialog. European date formats are dd/MM/yyyy and dd/MM/yyyy HH:mm:ss.

- If your computer's locale is east of Greenwich Mean Time (GMT), we recommend that you change your computer setting to GMT in order to avoid date adjustments when inserting or updating records.
- Only dates within a certain range are valid. The earliest valid date is 1700-01-01T00:00:00Z GMT, or just after midnight on January 1, 1700. The latest valid date is 4000-12-31T00:00:00Z GMT, or just after midnight on December 31, 4000. These values are offset by your time zone. For example, in the Pacific time zone, the earliest valid date is 1699-12-31T16:00:00, or 4:00 PM on December 31, 1699.

Double

Standard double string

ID

A Salesforce ID is a case-sensitive 15-character or case—insensitive 18-character alphanumeric string that uniquely identifies a particular record.



Tip: To ensure data quality, make sure that all Salesforce IDs you enter in Data Loader are in the correct case.

Integer

Standard integer string

String

All valid XML strings; invalid XML characters are removed.

Export Data

You can use the Data Loader export wizard to extract data from a Salesforce object.

- 1. Open the Data Loader.
- 2. Click **Export**. If you want to also export archived activity records and soft-deleted records, click **Export All** instead.
- **3.** Enter your Salesforce username and password, and click **Log in**.
- **4.** When you're logged in, click **Next**. (You are not asked to log in again until you log out or close the program.)

- **5.** Choose an object. For example, select the Account object. If your object name isn't listed, select **Show all objects** to see all the objects that you can access. The objects are listed by localized label name, with the developer name in parentheses. For object descriptions, see the *SOAP API Developer Guide*.
- **6.** Select the CSV file to export the data to. You can choose an existing file or create a file.

If you select an existing file, the export replaces its contents. To confirm the action, click **Yes**, or choose another file by clicking **No**.

7. Click Next.

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise,
Performance, Unlimited,
Developer, and
Database.com Editions

USER PERMISSIONS

To export records:

Read on the records

To export all records:

Read on the records

Using Data Loader Export Data

8. Create a SOQL query for the data export. For example, select **Id** and **Name** in the query fields, and click **Finish**. As you follow the next steps, the CSV viewer displays all the Account names and their IDs. SOQL is the Salesforce Object Query Language. Similar to the SELECT command in SQL, with SOQL, you can specify the source object, a list of fields to retrieve, and conditions for selecting rows in the source object.

- **a.** Choose the fields you want to export.
- **b.** Optionally, select conditions to filter your dataset. If you do not select any conditions, all the data to which you have read access is returned.
- **c.** Review the generated query and edit if necessary.
- 1 Tip: You can use a SOQL relationship query to include fields from a related object. For example:

Select Name, Pricebook2Id, Pricebook2.Name, Product2Id, Product2.ProductCode FROM PricebookEntry WHERE IsActive = true

Or:

```
Select Id, LastName, Account.Name FROM Contact
```

When using relationship queries in the Data Loader, the fully specified field names are case-sensitive. For example, using ACCOUNT.NAME instead of Account.Name does not work.

Data Loader doesn't support nested queries or querying child objects. For example, queries similar to the following return an error:

```
SELECT Amount, Id, Name, (SELECT Quantity, ListPrice,
PriceBookEntry.UnitPrice, PricebookEntry.Name,
PricebookEntry.product2.Family FROM OpportunityLineItems)
FROM Opportunity
```

Also, Data Loader doesn't support queries that use polymorphic relationships. For example, the following query results in an error:

```
SELECT Id, Owner.Name, Owner.Type, Owner.Id, Subject FROM Case
```

9. Click **Finish**, then click **Yes** to confirm.

A progress information window reports the status of the operation. After the operation completes, a confirmation window summarizes your results.

10. To view the CSV file. click **View Extraction**, or to close, click **OK**.



- Data Loader currently does not support exporting attachments. As a workaround, use the weekly export feature in the online application to export attachments.
- If you select compound fields for export in the Data Loader, they cause error messages. To export values, use individual field components.

Define Data Loader Field Mappings

When you insert, delete, or update files, use the Mapping Dialog window to associate Salesforce fields with the columns of your CSV file. For more information, see Insert, Update, or Delete Data Using Data Loader on page 18.

- 1. To automatically match fields with columns, click **Auto-Match Fields to Columns**. The Data Loader populates the list at the bottom of the window based on the similarity of field and column names. For a delete operation, automatic matching works only on the ID field.
- 2. To manually match fields with columns, click and drag fields from the list of Salesforce fields at the top to the list of CSV column header names at the bottom. For example, if you are inserting new Account records where your CSV file contains the names of new accounts, click and drag the Name field to the right of the NAME column header field.
- **3.** Optionally, click **Save Mapping** to save this mapping for future use. Specify a name for the SDL mapping file.

If you select an existing file, the export replaces its contents. To confirm the action, click **Yes**, or choose another file by clicking **No**.

4. Click **OK** to use your mapping for the current operation.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, Developer, and Database.com Editions

Insert, Update, or Delete Data Using Data Loader

USER PERMISSIONS	
To insert records:	Create on the record
To update records:	Edit on the record
To upsert records:	Create or Edit on the record
To delete records:	Delete on the record
To hard delete records:	Delete on the record
To mass delete records:	Modify All Data

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, Developer, and Database.com Editions

Use the Data Loader wizards to add, modify, or delete records. The upsert wizard combines inserting and updating a record. If a record in your file matches an existing record, the existing record is updated with the values in your file. If no match is found, a new record is created. When you hard-delete records, the deleted records are not stored in the Recycle Bin and are eligible for deletion. For more information, see Configure Data Loader.

- 1. Open the Data Loader.
- 2. Click Insert, Update, Upsert, Delete, or Hard Delete. These commands are also listed in the File menu.
- **3.** Enter your Salesforce username and password. To log in, click **Log in**. When you are logged in, click **Next**. (Until you log out or close the program, you are not asked to log in again.)

If your organization restricts IP addresses, logins from untrusted IPs are blocked until they're activated. Salesforce automatically sends you an activation email that you can use to log in. The email contains a security token that you add to the end of your password. For example, if your password is mypassword, and your security token is xxxxxxxxxxx, you must enter mypasswordxxxxxxxxxx to log in.

Using Data Loader Perform Mass Updates

4. Choose an object. For example, if you are inserting Account records, select **Account**. If your object name does not display in the default list, select **Show all objects** to see a complete list of the objects that you can access. The objects are listed by localized label name, with the developer name noted in parentheses.

- Note: Data Loader deletes records based on the IDs in the CSV file, not the object selected.
- **5.** To select your CSV file, click **Browse**. For example, if you are inserting Account records, you could specify a CSV file called insertaccounts.csv containing a Name column for the names of the new accounts.
- **6.** Click **Next**. After the object and CSV file are initialized, click **OK**.
- 7. If you are performing an upsert, your CSV file must contain a column of ID values for matching against existing records. The column is either an external ID (a custom field with the External ID attribute) or ID (the Salesforce record ID).
 - **a.** From the dropdown list, select which field to use for matching. If the object has no external ID fields, ID is used. Click **Next** to continue.
 - **b.** If your file includes the external IDs of an object that has a relationship to your chosen object, enable that external ID for record matching by selecting its name from the dropdown list. If you make no selection, you can use the related object's ID field for matching by mapping it in the next step. Click **Next** to continue.
- **8.** Define how the columns in your CSV file map to Salesforce fields. To select an existing field mapping, click **Choose an Existing Map**. To create or modify a map, click **Create or Edit a Map**. Click **Next**.
- **9.** For each operation, the Data Loader generates two unique CSV log files. One file name starts with "success," and the other starts with "error." Click **Browse** to specify a directory for these files.
- **10.** To complete the operation, click **Finish**, and then click **Yes** to confirm. As the operation proceeds, a progress information window reports the status of the data movement.
- 11. To view your success or error files, click **View Successes** or **View Errors**. To close the wizard, click **OK**.



Гір:

- If you are updating or deleting large amounts of data, review Perform Mass Updates and Perform Mass Deletes for tips and best practices.
- There is a 5-minute limit to process 100 records when the Bulk API is enabled. If it takes longer than 10 minutes to process a file, the Bulk API places the remainder of the file back in the queue for later processing. If the Bulk API continues to exceed the 10-minute limit on subsequent attempts, the file is placed back in the queue and reprocessed up to 10 times before the operation is permanently marked as failed. Even if the processing fails, some records could have completed successfully, so check the results. If you get a timeout error when loading a file, split your file into smaller files and try again.

Perform Mass Updates

To update a large number of records at one time, we recommend the following steps:

- 1. Obtain your data by performing an export of the objects you wish to update, or by running a report. Make sure your report includes the record ID.
- **2.** As a backup measure, save an extra copy of the generated CSV file.
- 3. Open your working file in a CSV editor such as Excel, and update your data.
- **4.** Launch Data Loader and follow the update wizard. Note that matching is done according to record ID. See Insert, Update, or Delete Data Using Data Loader on page 18.
- **5.** After the operation, review your success and error log files. See Review Data Loader Output Files on page 22.

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

Using Data Loader Perform Mass Deletes

6. If you made a mistake, use the backup file to update the records to their previous values.

Perform Mass Deletes

To delete a large number of records at one time using Data Loader, we recommend the following steps:

- 1. As a backup measure, export the records you wish to delete, being sure to select all fields. (See Export Data on page 16.) Save an extra copy of the generated CSV file.
- **2.** Next, export the records you wish to delete, this time using only the record ID as the desired criterion.
- **3.** Launch the Data Loader and follow the delete or hard delete wizard. Map only the ID column. See Insert, Update, or Delete Data Using Data Loader on page 18.
- **4.** After the operation, review your success and error log files. See Review Data Loader Output Files on page 22.

EDITIONS

Available in: both Salesforce Classic and Lightning Experience

Available in: Enterprise,
Performance, Unlimited,
Developer, and
Database.com Editions

USER PERMISSIONS

To mass delete records:

Modify All Data

Upload Attachments

Use Data Loader to upload attachments to Salesforce.

Before uploading attachments, note the following:

- If you intend to upload with Bulk API, verify that Upload Bulk API Batch as Zip File on the **Settings** > **Settings** page is enabled.
- If you are migrating attachments from a source Salesforce org to a target org, begin by requesting a data export for the source org. On the Schedule Export page, select **Include Attachments** to include the Attachment.csv file in your export. You can use this CSV file to upload the attachments. For more information on the export service, see Export Backup Data from Salesforce.
- 1. Confirm that the CSV file you want to use for attachment importing contains these required columns. Each column represents a Salesforce field.
 - Parentld—Salesforce ID of the parent record
 - Name—Name of the attachment file, such as myattachment.jpg
 - Body—Absolute path to the attachment on your local drive

Make sure that the values in the Body column contain the full path of the attachments on your computer. For example, if an attachment named myattachment.jpg is the folder C:\Export, Body must specify C:\Export\myattachment.jpg. Your CSV file looks like this example:

```
ParentId, Name, Body
5003000000VDowAAG, attachment1.jpg, C:\Export\attachment1.gif
70130000000iNHAAY, attachment2.doc, C:\Export\files\attachment2.doc
500300000VDowAAG, attachment1.jpg, C:\Export\attachment word document.doc
```

The CSV file can also include other optional Attachment fields, such as Description.

2. Proceed with an insert or upsert operation (see Insert, Update, or Delete Data Using Data Loader on page 18). For the select data objects step, select **Show all Salesforce objects** and the attachment object name in the list.

Upload Content with the Data Loader

You can use Data Loader to bulk upload documents and links into libraries in Salesforce CRM Content. Before uploading documents or links, note the following.

- If you intend to upload with Bulk API, verify that Upload Bulk API Batch as Zip File on the **Settings** > **Settings** page is enabled.
- When you upload a document from your local drive using Data Loader, specify the path in the VersionData and PathOnClient fields in the CSV file. VersionData identifies the location and extracts the format, and PathOnClient identifies the type of document being uploaded.
- When you upload a link using the Data Loader, specify the URL in ContentUrl. Don't use PathOnClient or VersionData to upload links.
- You can't export content using the Data Loader.
- If you're updating content that you've already uploaded:
 - Perform the Insert function.
 - Include a ContentDocumentId column with an 18-character ID. Salesforce uses this information to determine that you're
 updating content. When you map the ContentDocumentId, the updates are added to the content file. If you don't include
 the ContentDocumentId, the content is treated as new, and the content file isn't updated.
- 1. Create a CSV file with the following fields.
 - Title file name.
 - Description (optional) file or link description.
 - Note: If there are commas in the description, use double quotes around the text.
 - VersionData complete file path on your local drive (for uploading documents only).
 - Note: Files are converted to base64 encoding on upload. This action adds approximately 30% to the file size.
 - PathOnClient complete file path on your local drive (for uploading documents only).
 - ContentUrl URL (for uploading links only).
 - OwnerId (optional) file owner, defaults to the user uploading the file.
 - FirstPublishLocationId library ID.
 - RecordTypeId record type ID.
 - Note: If you publish to a library that has restricted record types, specify RecordTypeId.

To determine the RecordTypeId values for your organization using Data Loader, follow the steps in Exporting Data. The following is a sample SOQL query:

Select Id, Name FROM RecordType WHERE SobjectType = 'ContentVersion'

To determine the RecordTypeId values for your organization using the AJAX Toolkit:

- a. Log in to Salesforce.
- **b.** Enter this URL in your browser: http://instanceName.salesforce.com/soap/ajax//debugshell.html. Enter the instanceName for your organization. You can see the instanceName in the URL field of your browser after logging in to Salesforce.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, and Developer Editions **c.** In the AJAX Toolkit Shell page, type:

sforce.connection.describeSObject("ContentVersion")

- d. Press Enter.
- e. Click the arrows for record Type Infos.

The RecordTypeId values for your organization are listed.

TagsCsv - (optional) tag.

A sample CSV file is:

2. Upload the CSV file for the ContentVersion object (see Insert, Update, or Delete Data Using Data Loader on page 18). All documents and links are available in the specified library.

Review Data Loader Output Files

After an import or export, Data Loader generates two CSV output files that contain the results of the operation. One file name starts with "success," and the other starts with "error." You can use the Data Loader CSV file viewer to open the files.

- 1. Choose View > View CSV.
- **2.** Specify the number of rows to view. Each row in the CSV file corresponds to one Salesforce record. The default is 1,000.
- **3.** To view a specific CSV file, click **Open CSV**. To view the last success file, click **Open Success**. To view the last error file, click **Open Error**.
- **4.** To open the file in an external program, such as Excel, click **Open in External Program**.

The success file contains all the successfully loaded records. The file includes a column with the newly generated record IDs. The error file contains all the rejected records. The file has a column that describes why the load failed.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise,
Performance, Unlimited,
Developer, and
Database.com Editions

- Note: If the object you are exporting has a column named "success" or "error," your output file columns could display incorrect information. To avoid this problem, rename the columns.
- 5. To return to the CSV Chooser window, click **Close**. To exit the window, click **OK**.
- Note: To generate success files when exporting data, select Generate status files for exports. For more information, see Configure Data Loader on page 8.

Data Import Dates

Limits for importing data with Data Loader.

The following limits apply to data imported using Data Loader.

Only dates within a certain range are valid. The earliest valid date is 1700-01-01T00:00:00Z GMT, or just after midnight on January 1, 1700. The latest valid date is 4000-12-31T00:00:00Z GMT, or just after midnight on December 31, 4000. These values are offset by your time zone. For example, in the Pacific time zone, the earliest valid date is 1699-12-31T16:00:00, or 4:00 PM on December 31, 1699.

When using Data Loader version 28.0 and later, the maximum field size for imported CSV files is 32,000 characters.

View the Data Loader Log File

If you need to investigate a problem with Data Loader, or if requested by Salesforce Customer Support, you can access log files that track the operations and network connections made by Data Loader.

The log file, sdl.log, contains a detailed chronological list of Data Loader log entries. Log entries marked "INFO" are procedural items, such as logging in to and out of Salesforce. Log entries marked "ERROR" are problems such as a submitted record missing a required field. The log file can be opened with commonly available text editor programs, such as Microsoft Notepad.

If you are using Data Loader for Windows, view the log file by entering <code>%TEMP%\sdl.log</code> in either the Run dialog or the Windows Explorer address bar.

If you are using Data Loader for Mac OSX, view the log file by opening terminal and entering open \$TMPDIR/sdl.log.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: **Enterprise**, **Performance**, **Unlimited**, **Developer**, and **Database.com** Editions

If you are having login issues from the command line, ensure that the password provided in the configuration parameters is encrypted. If you are having login issues from the UI, you may need to obtain a new security token.

Configure the Data Loader Log File

You can customize the Data Loader log file for advanced troubleshooting and tracking.

The log-conf.xml file is included with the Data Loader installer version 35.0.

- In Windows, the log-conf.xml file is at
 C:\Users\{userName}\dataloader\version\configs
- In macOS, the log-conf.xml file is at /Users/{userName}/dataloader/version/configs

Change <code>@LOG_LEVEL@</code> to TRACE, DEBUG, INFO, WARN, ERROR, or FATAL for the needed level of log tracking. For Log4J log levels, see

https://logging.apache.org/log4j/2.0/manual/architecture.html.

To implement enhanced logging, use a copy of log-conf.xml.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

CHAPTER 6 Running in Batch Mode (Windows Only)

In this chapter ...

- Installed Directories and Files
- Encrypt from the Command Line
- Upgrade Your Batch Mode Interface
- Run Batch File With Windows Command-Line Interface
- Configure Batch Processes
- Data Loader Process Configuration Parameters
- Data Loader Command-Line Operations
- Configure Database Access
- Map Columns
- Run Individual Batch Processes

You can run Data Loader in batch mode from the Windows command line. Batch mode runs a series of Data Loader processes in a certain order using a batch file. You can rerun the same sequence of processes using an executable .bat file.

- Note: The Data Loader command-line interface is supported for Windows only.
- Note: If you're batch mode from the command line with a version earlier than 8.0, see Upgrade Your Batch Mode Interface on page 26.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Installed Directories and Files

In version 8.0 and later, installing the Data Loader adds several directories under the installation directory that are needed for automated batch processing.



Note: The Data Loader command-line interface is supported for Windows only.

bin

Contains the batch files encrypt.bat for encrypting passwords and process.bat for running batch processes.

For information on running Data Loader from the command-line, see Run Batch File With Windows Command-Line Interface on page 26.

configs

The default configuration directory. Contains the configuration files config.properties, Loader.class, and log-conf.xml.

The config.properties file that is generated when you modify the Settings dialog in the graphical user interface is located at C:\Users\{userName}\dataloader\version\configs.

Data Loader runs the operation, file, or map listed in the configuration file that you specify. If you don't specify a configuration directory, the current directory is used.

samples

Contains subdirectories of sample files for reference.

File Path Convention

The file paths provided in these topics start one level below the installation directory. For example, \configs means C:\Users\{userName}\dataloader\version\configs, provided you accepted the default installation directory. If you installed the program in a different location, use that directory path.

Encrypt from the Command Line

Data Loader offers an encryption utility to secure passwords specified in configuration files. While Data Loader does not handle encryption directly, data in transit is encrypted when using a secure connection such as HTTPS.



Note: The Data Loader command-line interface is supported for Windows only.

When running Data Loader in batch mode from the command line, you must encrypt the following configuration parameters:

- sfdc.password
- sfdc.proxyPassword
- 1. Open a command prompt, and navigate to the bin subfolder of your Data Loader installation folder.
- 2. Run encrypt.bat.
- **3.** At the command line, follow the prompts provided to execute the following actions.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, Developer, and Database.com Editions

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Generate a key: -k [path to key file]

Generates a key file, and saves it in <code>%userprofile%\.dataloader\dataLoader.key</code> if the path is not specified. Store this file with care as you use it for encryption and decryption.

Encrypt text: -e
plain text> <path to key file>
Generates an encrypted version of the text. Provide a key file for the encryption.

Decrypt text: -d <encrypted text> <path to key file> Decrypts the text using the key file.

Upgrade Your Batch Mode Interface



Note: The Data Loader command-line interface is supported for Windows only.

The batch mode interface in Data Loader versions 8.0 and later aren't backward-compatible with earlier versions. If you're using a version earlier than 8.0 to run batch processes, your options are as follows:

Maintain the old version for batch use

Do not uninstall your old version of Data Loader. Continue to use that version for batch processes. You can't take advantage of newer features such as database connectivity, but your integrations will continue to work. Optionally, install the new version alongside the old version and dedicate the old version solely to batch processes.

Generate a new config.properties file from the new GUI

If you originally generated your config.properties file from the graphical user interface, use the new version to set the same properties and generate a new file. Use this new file with the new batch mode interface. For more information, see Run Batch File With Windows Command-Line Interface on page 26.

Manually update your config.properties file

If your old config.properties file was created manually, you must manually update it for the new version. For more information, see Installed Directories and Files on page 25.

Run Batch File With Windows Command-Line Interface

For automated batch operations, such as nightly scheduled loads and extractions, run Data Loader from the Windows command-line.



Note: The Data Loader command-line interface is supported for Windows only.

Include your encrypted password in the configuration file to run a batch operation. For more information, see Data Loader Command Line Introduction on page 45 and Encrypt from the Command Line on page 25. From the command line, navigate to the bin directory, and enter process.bat. This file takes the following parameters.

- The directory containing config.properties
- The name of the batch process bean contained in process-conf.xml

You use the process-conf.xml file to configure batch processing. Set the name of the process in the bean element's id attribute: (for example < bean id="myProcessName">).

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, Developer, and Database.com Editions

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

You can change parameters at run time by giving param=value as program arguments. For example, adding process.operation=insert to the command changes the configuration at run time.

The process.bat file supports running JAR with up to two parameters. The format for two parameters is:

java -cp ..\dataloader-xx.0.0-uber.jar -Dsalesforce.config.dir=<configdir>
com.salesforce.dataloader.process.ProcessRunner <operation> parameterName1=ParemeterValue1
parameterName2=ParemeterValue2

An example of running the JAR with two parameters is:

```
"%JAVA_HOME%\bin\java" -cp ..\dataloader-44.1.0-uber.jar
-Dsalesforce.config.dir="C:\Users\username\dataloaderconfig"
com.salesforce.dataloader.process.ProcessRunner accountInsert
process.outputSuccess=c:\temp\accountInsert_success.csv
process.outputError=c:\temp\accountInsert_error.csv
```



Tip: If you experience login issues in the command-line interface after upgrading Data Loader, try encrypting your password again to solve the problem. For information, see Encrypt from the Command Line on page 25.

Configure Batch Processes



Note: The Data Loader command-line interface is supported for Windows only.

Use \samples\conf\process-conf.xml to configure your Data Loader processes, which are represented by ProcessRunner beans. A process should have ProcessRunner as the class attribute and the following properties set in the configuration file:

name

Sets the name of the ProcessRunner bean. This value is also used as the non-generic thread name and for configuration backing files (see below).

configOverrideMap

A property of type map where each entry represents a configuration setting: the key is the setting name; the value is the setting value.

enableLastRunOutput

If set to true (the default), output files containing information about the last run, such as sendAccountsFile_lastrun.properties, are generated and saved to the location specified by lastRunOutputDirectory. If set to false, the files are not generated or saved.

lastRunOutputDirectory

The directory location where output files containing information about the last run, such as sendAccountsFile_lastrun.properties, are written. The default value is \conf. If enableLastRunOutput is set to false, this value is not used because the files are not generated.

The configuration backing file stores configuration parameter values from the last run for debugging purposes, and is used to load default configuration parameters in <code>config.properties</code>. The settings in <code>configOverrideMap</code> take precedence over those in the configuration backing file. The configuration backing file is managed programmatically and does not require any manual edits.

For the names and descriptions of available process configuration parameters, see Data Loader Process Configuration Parameters on page 28.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Data Loader Process Configuration Parameters



Note: The Data Loader command-line interface is supported for Windows only.

When running Data Loader from the command line, you can specify the following configuration parameters in the process-conf.xml file. In some cases, the parameter is also represented in the UI at **Settings** > **Settings**.



Tip: A sample process-conf.xml file is in the \samples directory that's installed with Data Loader.

Parameter Name	Data Type	Equivalent Option in Settings Dialog	Description
dataAccess.readUTF8	boolean	Read all CSVs with UTF-8 encoding	Select this option to force files to open in UTF-8 encoding, even if they were saved in a different format. Sample value: true
dataAccess.writeUTF8	boolean	Write all CSVs with UTF-8 encoding	Select this option to force files to be written in UTF-8 encoding. Sample value: true
dataAccess.name	string	Not applicable (N/A)	Name of the data source to use, such as a CSV file name. For databases, use the name of the database configuration in database-conf.xml. Sample value: c:\dataloader\data\extractIead.csv
			Number of records read from the database at a time. The maximum value is 200.
dataAccess.readBatchSize	integer	N/A	Sample value: 50
			Standard or custom data source type. Standard types are csvWriter, csvRead, databaseWrite, and databaseRead.
dataAccess.type	string	N/A	Sample value: csvWrite

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Parameter Name	Data Type	Equivalent Option in Settings Dialog	Description
			Number of records written to the database at a time. The maximum value is 2,000. Note the implication for a large parameter value: if an error occurs, all records in the batch are rolled back. In contrast, if the value is set to 1, each record is processed individually (not in batch) and errors are specific to a given record. We recommend setting the value to 1 when you need to diagnose problems with writing to a database.
dataAccess.writeBatchSize	integer	N/A	Sample value: 500
loader.csvComma	boolean	Allow comma as a CSV delimiter	Select this option if your CSV file uses commas to delimit records.
loader.csvTab	boolean	Allow tab as a CSV delimiter	Select this option if your CSV file uses tab characters to delimit records.
loader.csvOther	boolean	Allow other characters as CSV delimiters	Select this option if your CSV file uses a character other than a comma or tab to delimit records.
loader.csvOtherValue	string	Other delimiters (enter multiple values with no separator; for example, !+?)	The characters in this field are used only if the Allow other characters as CSV delimiters option is selected. For example, if you use the (pipe) character to delimit data records, enter that character in this field.
<pre>process.enableExtractStatusOutput</pre>	boolean	Generate status files for exports	Select this option to generate success and error files when exporting data. Sample value: true
process.enableLastRunOutput	boolean	N/A	When running Data Loader in batch mode, you can disable the generation of output files such as

Parameter Name	Data Type	Equivalent Option in Settings Dialog	Description
			sendAccountsFile_lastRun.properties. Files of this type are saved by default to the conf directory. To stop the writing of these files, set this option to false.
			Alternatively, you can change the location of the directory where these files are saved, using process.lastRunOutputDirectory.
			Sample value: true
			Name of the file that contains the encryption key. This parameter is required in Data Loader version 43.0 and later. See Encrypt from the Command Line on page 25.
process.encryptionKeyFile	string (file name)	N/A	Sample value: c:\Users\{user}\.dataloader\dataloader.key
			The initial setting for the process.lastRunDate parameter, which can be used in a SQL string and is automatically updated when a process has run successfully. For an explanation of the date format syntax, see Date Formats on page 15.
process.initialLastRunDate	date	N/A	Format must be yyyy-MM-ddTHH:mm:ss.SSS+/-HHmm.For example: 2006-04-13T13:50:32.423-0700
			When running Data Loader in batch mode, you can change the location where output files such as sendAccountsFile_lastRun.properties are written. Files of this type are saved by default to the \conf directory. To change the location, change the value of this option to the full path where you want the output files written.
<pre>process.lastRunOutputDirectory</pre>	string (directory)	NI/A	Alternatively, you can stop the files from being written, using process.enableLastRunOutput.
Process. rasekanoucpuestrectory	(directory)	Start at	If your last operation failed, you can use this setting to begin where the last successful operation finished.
process.loadRowToStartAt	number	row	Sample value: 1008

Parameter Name	Data Type	Equivalent Option in Settings Dialog	Description
			Name of the field mapping file to use. See Map Columns on page 41.
process.mappingFile	string (file name)	N/A	Sample value: c:\dataloader\conf\accountExtractMap.sdl
			The operation to perform. See Data Loader Command-Line Operations on page 36.
process.operation	string	N/A	Sample value: extract
	string		The directory where "success" and "error" output files are saved. The file names are automatically generated for each operation unless you specify otherwise in process-conf.xml.
process.statusOutputDirectory	string (directory)	N/A	Sample value: c:\dataloader\status
			The name of the CSV file that stores error data from the last operation.
	string (file		Sample value:
process.outputError	name)	N/A	c:\dataloader\status\myProcessErrors.csv
			The name of the CSV file that stores success data from the last operation. See also
			<pre>process.enableExtractStatusOutput on page 29.</pre>
process.outputSuccess	string (file name)	N/A	Sample value: c:\dataloader\status\myProcessSuccesses.csv
		Use European	Select this option to support the date formats dd/MM/yyyy and dd/MM/yyyy HH:mm:ss.
process.useEuropeanDates	boolean	date format	Sample value: true
		Aggienment	Specify the ID of the assignment rule to use for inserts, updates, and upserts. This option applies to inserts, updates, and upserts on cases and leads. With the original territory management feature, it also applies to updates on accounts if your organization has territory assignment rules on accounts. The assignment rule overrides Owner values in your CSV file.
sfdc.assignmentRule	string	Assignment rule	Sample value: 03Mc00000026J7w

Parameter Name	Data Type	Equivalent Option in Settings Dialog	Description
			The number of milliseconds to wait between successive checks to determine if the asynchronous Bulk API operation is complete or how many records have been processed. See also
			<pre>sfdc.useBulkApi. We recommend a value of 5000.</pre>
sfdc.bulkApiCheckStatusInterval	integer	N/A	Sample value: 5000
		Enable serial mode for	To use serial processing instead of parallel processing for Bulk API, select this option. Processing in parallel can cause database contention. When contention is severe, the load can fail. Serial mode processes batches one at a time, however it can increase the processing time for a load. See also sfdc.useBulkApi. Sample value: false
sfdc.bulkApiSerialMode	boolean	Bulk API	
		Upload Bulk API	Select this option to use Bulk API to upload zip files containing binary attachments, such as Attachment records or Salesforce CRM Content. See also sfdc.useBulkApi.
sfdc.bulkApiZipContent	boolean	Batch as Zip File	Sample value: true
			The number of seconds to wait for a connection during API calls.
sfdc.connectionTimeoutSecs	integer	N/A	Sample value: 60
			If true, enables SOAP message debugging. By default, messages are sent to STDOUT unless you specify an alternate location in sfdc.debugMessagesFile.
sfdc.debugMessages	boolean	N/A	Sample value: false
			See process.enableExtractStatusOutput on page 29. Stores SOAP messages sent to or from Salesforce. As messages are sent or received, they are appended to the end of the file. As the file does not have a size limit, monitor your available disk storage appropriately.
sfdc.debugMessagesFile	string (file name)	N/A	Sample value: \lexiloader\status\sfdcSoapTrace.log

Parameter Name	Data Type	Equivalent Option in Settings Dialog	Description
			If true, enables repeated attempts to connect to Salesforce servers. See <pre>sfdc.maxRetries</pre> on page 34 and <pre>sfdc.minRetrySleepSecs</pre> on page 34.
sfdc.enableRetries	boolean	N/A	Sample value: true
			Enter the URL of the Salesforce server with which you want to communicate. For example, if you are loading data into a sandbox, change the URL to https://test.salesforce.com.
sfdc.endpoint	URL	Server host	Sample production value: https://login.salesforce.com/services/Soap/u/
			The Salesforce object used in the operation.
sfdc.entity	string	N/A	Sample value: Lead
			Used in upsert operations; specifies the custom field with the "External ID" attribute that is used as a unique identifier for data matching.
sfdc.externalIdField	string	N/A	Sample value: LegacySKUc
		Query request	In a single export or query operation, records are returned from Salesforce in increments of this size. Larger values can improve performance but use more memory on the client. Sample value: 500
sfdc.extractionRequestSize	integer	size	The SOQL query for the data export.
sfdc.extractionSOQL	string	N/A	Sample value: SELECT Id, LastName, FirstName, Rating, AnnualRevenue, OwnerId FROM Lead
sfdc.insertNulls	boolean	Insert null values	Select this option to insert blank mapped values as null values during data operations. When you are updating records, this option instructs Data Loader to overwrite existing data in mapped fields. Sample value: false
sfdc.loadBatchSize	integer	Batch size	In a single insert, update, upsert, or delete operation, records moving to or from Salesforce are processed in increments of this size. The maximum is 200 records. We recommend a value between 50 and 100.

Parameter Name	Data Type	Equivalent Option in Settings Dialog	Description
			Sample value: 100
			The maximum number of repeated attempts to connect to Salesforce. See sfdc.enableRetries on page 33.
sfdc.maxRetries	integer	N/A	Sample value: 3
			The minimum number of seconds to wait between connection retries. The wait time increases with each try. See sfdc.enableRetries on page 33.
sfdc.minRetrySleepSecs	integer	N/A	Sample value: 2
			Compression enhances the performance of Data Loader and is turned on by default. You might want to disable compression when debugging the underlying SOAP messages. To turn off compression, enable this option.
sfdc.noCompression	boolean	Compression	Sample value: false
	encrypted		An encrypted Salesforce password that corresponds to the username provided in sfdc.username. This parameter is required in Data Loader version 43.0 and later. See also Encrypt from the Command Line on page 25.
sfdc.password	string	N/A	Sample value: 4285b36161c65a22
sfdc.proxyHost	URL	Proxy host	The host name of the proxy server, if applicable. Sample value: http://myproxy.internal.company.com
sfdc.proxyPassword	encrypted string	Proxy password	An encrypted password that corresponds to the proxy username provided in sfdc.proxyUsername. See also Encrypt from the Command Line on page 25. Sample value: 4285b36161c65a22
sfdc.proxyPort	integer	Proxy	The proxy server port. Sample value: 8000
sfdc.proxyUsername	string	Proxy username	The username for proxy server authentication. Sample value: jane.doe

Parameter Name	Data Type	Equivalent Option in Settings Dialog	Description
sfdc.resetUrlOnLogin	boolean	Reset URL on Login	By default, Salesforce resets the URL after login to the one specified in <pre>sfdc.endpoint</pre> . To turn off this automatic reset, disable this option by setting it to false. Valid values: <pre>true</pre> (default), false
			Specify how many seconds Data Loader waits to receive a response back from the server before returning an error for the request.
sfdc.timeoutSecs	integer	Timeout	Sample value: 540
			If a date value does not include a time zone, this value is used.
			• If no value is specified, the time zone of the computer where Data Loader is installed is used.
			• If an incorrect value is entered, GMT is used as the time zone and this fact is noted in the Data Loader log.
			Valid values are any time zone identifier which can be passed to the Java <pre>getTimeZone (java.lang.String)</pre> method. The value can be a full name such as America/Los_Angeles, or a custom ID such as GMT-8:00.
sfdc.timezone	string	Time Zone	You can retrieve the default value by running the TimeZone.getDefault() method in Java. This value is the time zone on the computer where Data Loader is installed.
			Select this option to truncate data in the following types of fields when loading that data into Salesforce: Email, Multi-select Picklist, Phone, Picklist, Text, and Text (Encrypted).
			In Data Loader versions 14.0 and earlier, Data Loader truncates values for fields of those types if they are too large. In Data Loader version 15.0 and later, the load operation fails if a value is specified that is too large.
sfdc.truncateFields	boolean	Allow field truncation	Selecting this option allows you to specify that the previous behavior, truncation, be used instead of the new behavior in Data Loader versions 15.0 and later.

Parameter Name	Data Type	Equivalent Option in Settings Dialog	Description
			This option is selected by default and has no effect in versions 14.0 and earlier.
			This option is not available if the Use Bulk API option is selected. In that case, the load operation fails for the row if a value is specified that is too large for the field.
			Sample value: true
			Select this option to use Bulk API to insert, update, upsert, delete, and hard-delete records. Bulk API is optimized to load or delete many records asynchronously. It's faster than the default SOAP-based API due to parallel processing and fewer network round-trips. See also sfdc.bulkApiSerialMode.
sfdc.useBulkApi	boolean	Use Bulk API	Sample value: true
			Salesforce username. See sfdc.password.
sfdc.username	string	N/A	Sample value: jdoe@mycompany.com

Data Loader Command-Line Operations



Note: The Data Loader command-line interface is supported for Windows only.

When running Data Loader in batch mode from the command line, several operations are supported. An operation represents the flow of data between Salesforce and an external data source, such as a CSV file or database. You can use the following operations. Enter values in the process.operation parameter in lowercase

Operation	Description
extract	Uses the Salesforce Object Query Language to export a set of records from Salesforce. The exported data is written to a data source. Soft-deleted records are not included.
extract all	Uses SOQL to export a set of records from Salesforce, including existing and soft-deleted records. The exported data is written to a data source.
insert	Loads data from a data source into Salesforce as new records.
update	Loads data from a data source into Salesforce, and updates existing records with matching ID fields.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Operation	Description
upsert	Loads data from a data source into Salesforce. Existing records with a matching custom external ID field are updated. Records without matches are inserted as new records.
delete	Loads data from a data source into Salesforce, and deletes existing records with matching ID fields. Deleted records are moved to the Recycle Bin.
hard delete	Loads data from a data source into Salesforce, and deletes existing records with matching ID fields without first storing them in the Recycle Bin.

Configure Database Access



Note: The Data Loader command-line interface is supported for Windows only.

When you run Data Loader in batch mode from the command line, use \samples\conf\database-conf.xml to configure database access objects, which you use to extract data directly from a database.

DatabaseConfig Bean

The top-level database configuration object is the DatabaseConfig bean, which has the following properties:

sqlConfig

The SQL configuration bean for the data access object that interacts with a database.

dataSource

The bean that acts as database driver and authenticator. It must refer to an implementation of javax.sql.DataSource such as org.apache.commons.dbcp.BasicDataSource.

The following code is an example of a DatabaseConfig bean:

DataSource

The DataSource bean sets the physical information needed for database connections. It contains the following properties:

driverClassName

The fully qualified name of the implementation of a JDBC driver.

url

The string for physically connecting to the database.

username

The username for logging in to the database.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

password

The password for logging in to the database.

Depending on your implementation, additional information may be required. For example, use org.apache.commons.dbcp.BasicDataSource when database connections are pooled.

The following code is an example of a DataSource bean:

Versions of Data Loader from API version 25.0 onwards do not come with an Oracle JDBC driver. Using Data Loader to connect to an Oracle data source without a JDBC driver installed will result in a "Cannot load JDBC driver class" error. To add the Oracle JDBC driver to Data Loader:

- Download the latest JDBC driver from http://www.oracle.com/technetwork/database/features/jdbc/index-091264.html.
- Copy the JDBC .jar file to data loader install folder/java/bin.

Spring Framework



Note: The Data Loader command-line interface is supported for Windows only.

The Data Loader configuration files are based on the Spring Framework, which is an open-source, full-stack Java/J2EE application framework.

The Spring Framework allows you to use XML files to configure beans. Each bean represents an instance of an object; the parameters correspond to each object's setter methods. A typical bean has the following attributes:

id

Uniquely identifies the bean to XmlBeanFactory, which is the class that gets objects from an XML configuration file.

class

Specifies the implementation class for the bean instance.

For more information on the Spring Framework, see the official documentation and the support forums. Note that Salesforce cannot guarantee the availability or accuracy of external websites.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Data Access Objects



Note: The Data Loader command-line interface is supported for Windows only.

When running Data Loader in batch mode from the command line, several data access objects are supported. A data access object allows access to an external data source outside of Salesforce. They can implement a read interface (DataReader), a write interface (DataWriter), or both. See the following list of object names and descriptions.

Allows the reading of a comma or tab-delimited file. There should be a header row at the top of the file that describes each column.

csvWrite

Allows writing to a comma-delimited file. A header row is added to the top of the file based on the column list provided by the caller.

databaseRead

Allows the reading of a database. Use database-conf.xml to configure database access.

databaseWrite

Allows writing to a database. Use database-conf.xml to configure database access.

SQL Configuration



Note: The Data Loader command-line interface is supported for Windows only.

When running Data Loader in batch mode from the command line, the SqlConfig class contains configuration parameters for accessing specific data in the database. As shown in the code samples below, queries and inserts are different but very similar. The bean must be of type com.salesforce.dataloader.dao.database.SqlConfig and have the following properties:

sqlString

The SQL code to be used by the data access object.

The SQL can contain replacement parameters that make the string dependent on configuration or operation variables. Replacement parameters must be delimited on both sides by "@" characters. For example, @process.lastRunDate@.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: **Enterprise**, Performance, Unlimited, Developer, and **Database.com** Editions

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: **Enterprise**, Performance, Unlimited, Developer, and **Database.com** Editions

sqlParams

A property of type map that contains descriptions of the replacement parameters specified in sqlString. Each entry represents one replacement parameter: the key is the replacement parameter's name, the value is the fully qualified Java type to be used when the parameter is set on the SQL statement. Note that "java.sql" types are sometimes required, such as java.sql.Date instead of java.util.Date. For more information, see the official JDBC API documentation.

columnNames

Used when queries (SELECT statements) return a JDBC ResultSet. Contains column names for the data outputted by executing the SQL. The column names are used to access and return the output to the caller of the DataReader interface.

SQL Query Bean Example

<bean id="accountMasterSql"</pre> class="com.salesforce.dataloader.dao.database.SqlConfig"

```
singleton="true">
    cproperty name="sqlString"/>
       <value>
           SELECT distinct
               '012x000000001j7' recordTypeId,
               accounts.account number,
               org.organization name,
               concat (concat(parties.address1, ' '), parties.address2) billing address,
               locs.city,
               locs.postal code,
               locs.state,
               locs.country,
               parties.sic code
            from
               ar.hz cust accounts accounts,
               ar.hz organization profiles org,
               ar.hz parties parties,
               ar.hz_party_sites party_sites,
               ar.hz locations locs
           where
               accounts.PARTY ID = org.PARTY ID
               and parties.PARTY ID = accounts.PARTY ID
               and party sites.PARTY ID = accounts.PARTY ID
               and locs.LOCATION ID = party sites.LOCATION ID
               and (locs.last_update_date > @process.lastRunDate@ OR
accounts.last update date > @process.lastRunDate@
       </value>
   </property>
   columNames">
       st>
            <value>recordTypeId</value>
           <value>account number</value>
           <value>organization name</value>
           <value>billing address</value>
            <value>city</value>
           <value>postal code</value>
           <value>state</value>
           <value>country</value>
           <value>sic code</value>
       </list>
   </property>
   property name="sqlParams">
           <entry key="process.lastRunDate" value="java.sql.Date"/>
   </property>
</bean>
```

SQL Insert Bean Example

```
<bean id="partiesInsertSql"
  class="com.salesforce.dataloader.dao.database.SqlConfig"</pre>
```

Map Columns



Note: The Data Loader command-line interface is supported for Windows only.

When running Data Loader in batch mode from the command line, you must create a properties file that maps values between Salesforce and data access objects.

- 1. Create a new mapping file and give it an extension of .sdl.
- 2. Observe the following syntax:
 - On each line, pair a data source with its destination.
 - In an import file, put the data source on the left, an equals sign (=) as a separator, and the destination on the right. In an export file, put the destination on the left, an equals sign (=) as a separator, and the data source on the right.
 - Data sources can be either column names or constants. Surround constants with double quotation marks, as in "sampleconstant". Values without quotation marks are treated as column names.
 - Destinations must be column names.
 - You may map constants by surrounding them with double quotation marks, as in:

```
"Canada"=BillingCountry
```

3. In your configuration file, use the parameter process.mappingFile to specify the name of your mapping file.



Note: If your field name contains a space, you must escape the space by prepending it with a backslash (\). For example:

```
Account\ Name=Name
```

Column Mapping Example for Data Insert

The Salesforce fields are on the right.

```
SLA__C=SLA__c
BILLINGCITY=BillingCity
SYSTEMMODSTAMP=
```

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

OWNERID=OwnerId
CUSTOMERPRIORITY__C=CustomerPriority__c
ANNUALREVENUE=AnnualRevenue
DESCRIPTION=Description
BILLINGSTREET=BillingStreet
SHIPPINGSTATE=ShippingState

Column Mapping Example for Data Export

The Salesforce fields are on the left.

Id=account_number
Name=name
Phone=phone

Column Mapping for Constant Values

Data Loader supports the ability to assign constants to fields when you insert, update, and export data. If you have a field that should contain the same value for each record, you specify that constant in the .sdl mapping file instead of specifying the field and value in the CSV file or the export query.

The constant must be enclosed in double quotation marks. For example, if you're importing data, the syntax is "constantvalue"=field1.

If you have multiple fields that should contain the same value, you must specify the constant and the field names separated by commas. For example, if you're importing data, the syntax would be "constantvalue"=field1, field2.

Here's an example of an .sdl file for inserting data. The Salesforce fields are on the right. The first two lines map a data source to a destination field, and the last three lines map a constant to a destination field.

```
Name=Name
NumEmployees=NumberOfEmployees
"Aerospace"=Industry
"California"=BillingState, ShippingState
"New"=Customer_Type__c
```

A constant must contain at least one alphanumeric character.



Note: If you specify a constant value that contains spaces, you must escape the spaces by prepending each with a backslash (\). For example:

"Food\ &\ Beverage"=Industry

Run Individual Batch Processes

You can run one batch process at a time.



Note: The Data Loader command-line interface is supported for Windows only.

To start an individual batch process, use \bin\process.bat. The command-line requires the following parameters.

Configuration directory

The default is \conf.

To use an alternate directory, create a directory and add the following files to it.

- If your process is not interactive, copy process-conf.xml from \samples\conf.
- If your process requires database connectivity, copy database-conf.xml from \samples\conf.
- Copy config.properties from \conf.

Process name

The name of the ProcessRunner bean from \samples\conf\process-conf.xml.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, Developer, and Database.com Editions

Process Example

process ../conf accountMasterProcess



Note: To view tips and instructions, add -help to the command contained in process.bat.



Note: You can configure external process launchers, such as the Windows XP Scheduled Task Wizard, to run processes on a schedule.

CHAPTER 7 Command-Line Quick Start (Windows Only)

In this chapter ...

- Data Loader
 Command Line
 Introduction
- Prerequisites
- Step One: Create the Encryption Key File
- Step Two: Create the Encrypted Password
- Step Three: Create the Field Mapping File
- Step Four: Create the Configuration File
- Step Five: Import the Data



Note: The Data Loader command-line interface is supported for Windows only.

This quick start shows you how to use the Data Loader command-line functionality to import data.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Data Loader Command Line Introduction



Note: The Data Loader command-line interface is supported for Windows only.

In addition to using Data Loader interactively to import and export data, you can run it from the command line. You can use commands to automate the import and export of data.

This quick start shows you how to use the Data Loader command-line functionality to import data. Follow these steps.

- Step 1: Create the encryption key
- Step 2: Create the encrypted password for your login username
- Step 3: Create the Field Mapping File
- Step 4: Create a process-conf.xml file that contains the import configuration settings
- Step 5: Run the process and import the data

SEE ALSO:

Prerequisites

Prerequisites



Note: The Data Loader command-line interface is supported for Windows only.

To step through this quick start requires the following:

- Data Loader installed on the computer that runs the command-line process.
- The Java Runtime Environment (JRE) installed on the computer that runs the command-line process.
- Familiarity with importing and exporting data by using the Data Loader interactively through the user interface. This makes it easier to understand how the command-line functionality works.

Tip: When you install Data Loader, sample files are installed in the samples directory under the user's directory, for example,

C:\Users\{userName}\dataloader\version\samples\. Examples of files that are used in this quick start are in the \samples\conf directory.

SEE ALSO:

Data Loader Command Line Introduction Step One: Create the Encryption Key File

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise, Performance, Unlimited, Developer, and Database.com Editions

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Step One: Create the Encryption Key File




Note: The Data Loader command-line interface is supported for Windows only.

When you use Data Loader from the command line, there's no user interface. Therefore, you provide the information that you would enter in the user interface in a text file named process-conf.xml. For example, you add the username and password that Data Loader uses to log in to Salesforce. The password must be encrypted before you add it to the process-conf.xml file, and creating the key is the first step in that process.

- Open a command prompt window by selecting Start > All Programs > Accessories >
 Command Prompt. Alternatively, you can click Start > Run, enter cmd in the Open field,
 and click OK.
- **2.** In the command window, enter $cd \setminus to$ navigate to the root directory of the drive where Data Loader is installed.
- 3. Navigate to the Data Loader \bin directory by entering this command. Replace the file path with the path from your system.

 C:\Users\{userName}\dataloader\version\bin
- **4.** Create an encryption key file by entering the following command. Replace [path to key file] with the key file path. encrypt.bat -k [path to key file]



- Note: To see a list of command-line options for encrypt.bat, enter encrypt.bat on the command line.
- 5. Note the key file path. In this example, the path is C:\Users\IEUser\.dataloader\dataLoader.key.

 The encryption utility encrypts passwords but not data. HTTPS with TLS 1.0 or later encrypts data transmitted by the Apex Data Loader.

SEE ALSO:

Data Loader Command Line Introduction
Step Two: Create the Encrypted Password

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Step Two: Create the Encrypted Password

Note: The Data Loader command-line interface is supported for Windows only.

Create the encrypted password using the key file that you generated in the previous step.


1. In the same command prompt window, enter the following command. Replace password>
with the password that you use to log in to Salesforce in Data Loader. Replace <key file
path> with the file path you created in the previous step.

encrypt.bat -e <password> <key file path>

EDITIONS Available in:

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: **Enterprise**, **Performance**, **Unlimited**, **Developer**, and **Database.com** Editions



2. Copy the generated encrypted password. You use this value in a later step.

SEE ALSO:

Data Loader Command Line Introduction Step Three: Create the Field Mapping File

Step Three: Create the Field Mapping File



Note: The Data Loader command-line interface is supported for Windows only.

In this step, you create a mapping file with an <code>.sdl</code> file extension. In each line of the mapping file, pair a data source with its destination.

Copy the following to a text file and save it with a name of accountInsertMap.sdl.
 This is a data insert, so the data source is on the left of the equals sign and the destination field is on the right.

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise,
Performance, Unlimited,
Developer, and
Database.com Editions

#Mapping values
#Thu May 26 16:19:33 GMT 2011
Name=Name
NumberOfEmployees=NumberOfEmployees
Industry=Industry



Tip: For complex mappings, you can use the Data Loader user interface to map source and destination fields and then save those mappings to an .sdl file. This is done on the Mapping dialog box by clicking **Save Mapping**.

SEE ALSO:

Data Loader Command Line Introduction Step Four: Create the Configuration File

Step Four: Create the Configuration File



Note: The Data Loader command-line interface is supported for Windows only.

The process-conf.xml file contains the information that Data Loader needs to process the data. Each <bean> in the process-conf.xml file refers to a single process such as an insert, upsert, or export. Therefore, this file can contain multiple processes. In this step, you edit the file to insert accounts into Salesforce.

- Make a copy of the process-conf.xml file from the \samples\conf directory. Be sure to maintain a copy of the original because it contains examples of other types of Data Loader processing such as upserts and exports.
- 2. Open the file in a text editor, and replace the contents with the following XML:

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

```
<!DOCTYPE beans PUBLIC "-//SPRING//DTD BEAN//EN"</pre>
"http://www.springframework.org/dtd/spring-beans.dtd">
<beans>
    <bean id="accountInsert"</pre>
       class="com.salesforce.dataloader.process.ProcessRunner"
        singleton="false">
        <description>accountInsert job gets the account record from the CSV file
            and inserts it into Salesforce.</description>
        property name="name" value="accountInsert"/>
        configOverrideMap">
            <map>
                <entry key="sfdc.debugMessages" value="true"/>
                <entry key="sfdc.debugMessagesFile"</pre>
                    value="C:\DLTest\Log\accountInsertSoapTrace.log"/>
                <entry key="sfdc.endpoint" value="https://servername.salesforce.com"/>
                <entry key="sfdc.username" value="admin@Org.org"/>
                <!--Password below has been encrypted using key file,
                    therefore, it will not work without the key setting:
                    process.encryptionKeyFile.
                    The password is not a valid encrypted value,
                    please generate the real value using the encrypt.bat utility -->
                <entry key="sfdc.password" value="e8a68b73992a7a54"/>
                <entry key="process.encryptionKeyFile"</pre>
                    value="c:\Users\{user}\.dataloader\dataLoader.key"/>
                <entry key="sfdc.timeoutSecs" value="600"/>
                <entry key="sfdc.loadBatchSize" value="200"/>
                <entry key="sfdc.entity" value="Account"/>
                <entry key="process.operation" value="insert"/>
```

- 3. Modify the following parameters in the process-conf.xml file. For more information about the process configuration parameters, see Data Loader Process Configuration Parameters on page 28.
 - sfdc.endpoint—Enter the URL of the Salesforce instance for your organization; for example, https://yourInstance.salesforce.com/.
 - sfdc.username—Enter the username Data Loader uses to log in.
 - sfdc.password—Enter the encrypted password value that you created in step 2.
 - process.mappingFile—Enter the path and file name of the mapping file.
 - dataAccess. Name—Enter the path and file name of the data file that contains the accounts that you want to import.
 - sfdc.debugMessages—Currently set to true for troubleshooting. Set to false after your import is up and running.
 - sfdc.debugMessagesFile—Enter the path and file name of the command line log file.
 - process.outputSuccess—Enter the path and file name of the success log file.
 - process.outputError—Enter the path and file name of the error log file.
 - Warning: Use caution when using different XML editors to edit the process-conf.xml file. Some editors add XML tags to the beginning and end of the file, which causes the import to fail.

SEE ALSO:

Data Loader Command Line Introduction Step Five: Import the Data

Step Five: Import the Data

To insert records: Create on the record To update records: Edit on the record To upsert records: Create or Edit on the record To delete records: Delete on the record To hard delete records: Delete on the record

EDITIONS

Available in: Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise,
Performance, Unlimited,
Developer, and
Database.com Editions



Note: The Data Loader command-line interface is supported for Windows only.

Now that all the pieces are in place, you can run Data Loader from the command line and insert some new accounts.

1. Copy the following data to a file name accountInsert.csv. This is the account data that you import into your organization.

Name, Industry, NumberOfEmployees
Dickenson plc, Consulting, 120
GenePoint, Biotechnology, 265
Express Logistics and Transport, Transportation, 12300
Grand Hotels & Resorts Ltd, Hospitality, 5600

2. In the command prompt window, enter the following command:

process.bat "<file path to process-conf.xml>" process name>

- Replace < file path to process-conf.xml> with the path to the directory containing process-conf.xml.
- Replace <process name> with the process specified in process-conf.xml.

Your command should look something like this:

process.bat "C:\DLTest\Command Line\Config" accountInsert

After the process runs, the command prompt window displays success and error messages. You can also check the log files: insertAccounts_success.csv and insertAccounts_error.csv. After the process runs successfully, the insertAccounts_success.csv file contains the records that you imported, along with the ID and status of each record. For more information about the status files, see Review Data Loader Output Files on page 22.

SEE ALSO:

Data Loader Command Line Introduction

APPENDIX A Data Loader Third-Party Licenses

The following third-party licenses are included with the installation of Data Loader:

Technology	Version Number	License
Apache Jakarta Commons BeanUtils	1.7	http://www.apache.org/licenses/LICENSE-2.0
Apache Commons Database Connection Pooling (DBCP)	1.4	http://www.apache.org/licenses/LICENSE-2.0
Apache Log4j	1.2.17	http://www.apache.org/licenses/LICENSE-2.0
Eclipse SWT	4.5.1	http://www.eclipse.org/legal/epl-v10.html
Spring Framework	3.1.1	http://www.apache.org/licenses/LICENSE-2.0.txt

EDITIONS

Available in: both Salesforce Classic (not available in all orgs) and Lightning Experience

Available in: Enterprise,
Performance, Unlimited,
Developer, and
Database.com Editions



Note: Salesforce is not responsible for the availability or content of third-party websites.

INDEX

D
Data
import limits 22
Data Loader
date formats 15

L Limits data import 22